

# Quiet Mode

Several remote commands can activate Quiet Mode on certain probe stations for quiet probing. For details about Quiet Mode, see [Quiet Mode and Stepping](#) in the *Velox User Guide*.

You can use the following Velox remote commands to set Quiet Mode or read Quiet/AutoQuiet Mode status.

Status/Mode	Command	Parameter and Purpose
Read Status	<a href="#">ReadChuckStatus</a>	<b>IsQuiet</b> – If true, the stage is currently quiet, either manually or by <b>AutoQuiet</b> .
	<a href="#">ReadProbeStatus</a>	<b>IsQuiet</b> – If true, the stage is currently quiet, either manually or by <b>AutoQuiet</b> .
	<a href="#">ReadScopeStatus</a>	<b>IsQuiet</b> – If true, the stage is currently quiet, either manually or by <b>AutoQuiet</b> .
	<a href="#">ReadAuxStatus</a>	<b>QuietContact (FlagsMode)</b> – If true, the AUX site is in AutoQuiet Mode.

Status/Mode	Command	Parameter and Purpose
Set Mode	<a href="#">SetChuckMode</a>	<b>QuietContact</b> – If true, activates AutoQuiet Mode.
	<a href="#">SetProbeMode</a>	<b>AutoQuiet</b> – If true, activates AutoQuiet Mode.
	<a href="#">SetScopeMode</a>	<b>QuietMode</b> – If true, activates AutoQuiet Mode for the Scope. Scope motors go quiet when the Chuck is in contact.
	<a href="#">EnableMotorQuiet</a>	<b>WantQuietModeOn</b> – If true, activates QuietMode (the motor power is turned off for quiet probing).
	<a href="#">SetCameraQuiet</a>	<p>CM300/SUMMIT200 probe stations only:</p> <p><b>Active</b> – If true, activates the camera Quiet Mode. In mode, a digital output disconnects the Chuck, Platen, and Contact View camera's firewire/USB connection to the PC. You may need to add a 10-20 second delay for this option.</p> <p>For more information, see <a href="#">Quiet Mode and Stepping</a> Quiet Mode and Stepping in the <i>Velox User Guide</i>.</p>

---

# Quiet Mode Workflows

The following workflow examples use Quiet Mode with and without an eVue Digital Imaging system.

## Flow for Probe Stations Without Platen/ContactView Cameras

```
MoveToNextSite()  
  
{  
  
  StepNextDie  
  
  SetMicroLight 0 //light off  
  
  [Measure]  
  
  SetMicroLight 1 //light on  
  
}
```

## Flow for Probe Stations With Platen/ContactView Cameras

```
{  
  
  StepFirstDie  
  
  SetCameraQuiet 1  
  
  *delay 20000  
  
  SetMicroLight 0 //light off  
  
  MoveChuckContact  
  
  [Measure]  
  
  StepNextDie  
  
}
```